

Setting up E-Mail for Pocket pc


1. In the Home screen, select **Start**, and then tap **Messaging**



2. Tap on **Menu** located at bottom Left of your screen
Tap on **Tools**, and then tap **New Account** or Tap **option and get next window.**



3. Tap New Account



4. In "E-mail Setup (1/5)" window, enter your full email address (e.g., Deepak@email.com), and tap **Next**.



5. In "E-mail Setup (2/5)" window, your device may perform an auto configuration. When completed, tap **Next**.



6. In "E-mail Setup (3/5)" window, in "Your name" field, enter your name (e.g., Deepak Joshi)
 In "User name" field, enter your username (complete email address or just the First part of the mail address (depends on email provider)
 In "Password" field, enter your account password
 Check the **Save Password** box, and tap **Next**.



7. In "E-mail Setup (4/5)" window , in "Account type" pop-up menu, select **POP3 or IMAP4** (Depends on your email provider (if you do not know ask your service provider)
 In "Name" field, enter a name for the account (e.g., Give friendly name for email), and tap **Next**.



8. In "E-mail Setup (5/5)" window, in "Incoming mail " field, enter the incoming mail server provided by your email service provider
In "Outgoing mail" field, enter outgoing mail server provided by your email service provider.

In "Domain" field, (leave blank)

Tap **Options** button

Example of Port setting (if required)

Incoming mail: pop.gmail.com:995

Outgoing mail:smtp.gmail.com:587

Messaging

E-mail Setup (5/5)

Server information

Incoming mail: type the server address

Outgoing mail: type the server address

Domain: leave blank

Options

Back Finish

9. In "Options (1/3)" window, configure how often you want the device to check for messages (e.g., **15** minutes)
(Note: battery life decreases to less than a day with intervals under 15 minutes)

Under Connection pop-up menu, select **The Internet**

Tap **Next**

Messaging

Options (1/3)

Note that connecting automatically may result in higher connection charges.

Connect and check for messages every:

15 minute(s)

Connection: The Internet

Back Next

10. In "Options (2/3)" window, configure how far back you want to check (e.g., 3 days)

Check the **Require SSL connection** box (depends on the email service provider , check with your email service provider)

Check the **Outgoing mail requires authentication** box (depends on the email, service provider ,check with email service provider)

Leave **Use Separate Settings** box unchecked

Tap **Next**

Messaging

Options (2/3)

Only display messages from the last 3 days

Require SSL connection

Outgoing mail requires authentication

Use separate settings


Outgoing Settings

Back Next

11. In "Options (3/3)" window, select **Get message headers only** and **Include 2 KB of message body** (this will cut down how much data is downloaded)

Tap **Finish**

When asked if you would like to download mail for this new account now, click **Yes**. Your email should begin downloading to the device.



Congratulation